




Number Systems and Number Representation

Q: Why do computer programmers
confuse Christmas and Halloween?

A: Because $25 \text{ Dec} = 31 \text{ Oct}$



Goals of this Lecture



Help you learn (or refresh your memory) about:

- The binary, hexadecimal, and octal number systems
- Finite representation of unsigned integers
- Finite representation of signed integers
- Finite representation of rational (floating-point) numbers

Why?

- A power programmer must know number systems and data representation to fully understand C's **primitive data types**

Primitive values and
the operations on them

Agenda



Number Systems

Finite representation of unsigned integers

Finite representation of signed integers

Finite representation of rational (floating-point) numbers

The Decimal Number System



Name

- “decem” (Latin) \Rightarrow ten

Characteristics

- Ten symbols
 - 0 1 2 3 4 5 6 7 8 9
- Positional
 - $2945 \neq 2495$
 - $2945 = (2 \cdot 10^3) + (9 \cdot 10^2) + (4 \cdot 10^1) + (5 \cdot 10^0)$

(Most) people use the decimal number system

Why?

The Binary Number System



binary

adjective: being in a state of one of two mutually exclusive conditions such as on or off, true or false, molten or frozen, presence or absence of a signal.
From Late Latin *bīnārius* (“consisting of two”).

Characteristics

- Two symbols: 0 1
- Positional: $1010_B \neq 1100_B$

Most (digital) computers use the binary number system

Terminology

- **Bit:** a binary digit
- **Byte:** (typically) 8 bits
- **Nibble (or nybble):** 4 bits



Decimal-Binary Equivalence



<u>Decimal</u>	<u>Binary</u>
0	0
1	1
2	10
3	11
4	100
5	101
6	110
7	111
8	1000
9	1001
10	1010
11	1011
12	1100
13	1101
14	1110
15	1111

<u>Decimal</u>	<u>Binary</u>
16	10000
17	10001
18	10010
19	10011
20	10100
21	10101
22	10110
23	10111
24	11000
25	11001
26	11010
27	11011
28	11100
29	11101
30	11110
31	11111
...	...

Decimal-Binary Conversion



Binary to decimal: expand using positional notation

$$\begin{aligned} 100101_B &= (1 \cdot 2^5) + (0 \cdot 2^4) + (0 \cdot 2^3) + (1 \cdot 2^2) + (0 \cdot 2^1) + (1 \cdot 2^0) \\ &= 32 + 0 + 0 + 4 + 0 + 1 \\ &= 37 \end{aligned}$$

Most-significant
bit (msb)

Least-significant
bit (lsb)

~~Integer~~ Decimal-Binary Conversion



Integer

Binary to ~~decimal~~: expand using positional notation

$$\begin{aligned} 100101_B &= (1 \cdot 2^5) + (0 \cdot 2^4) + (0 \cdot 2^3) + (1 \cdot 2^2) + (0 \cdot 2^1) + (1 \cdot 2^0) \\ &= 32 + 0 + 0 + 4 + 0 + 1 \\ &= 37 \end{aligned}$$

These are integers

They exist as their pure selves
no matter how we might choose
to *represent* them with our
fingers or toes

Integer-Binary Conversion



Integer to binary: do the reverse

- Determine largest power of 2 that's \leq number; write template

$$37 = (? * 2^5) + (? * 2^4) + (? * 2^3) + (? * 2^2) + (? * 2^1) + (? * 2^0)$$

- Fill in template

$$37 = (1 * 2^5) + (0 * 2^4) + (0 * 2^3) + (1 * 2^2) + (0 * 2^1) + (1 * 2^0)$$

-32
5
-4
1
-1
0

100101_B

Integer-Binary Conversion



Integer to binary shortcut

- Repeatedly divide by 2, consider remainder

37	/	2	=	18	R	1
18	/	2	=	9	R	0
9	/	2	=	4	R	1
4	/	2	=	2	R	0
2	/	2	=	1	R	0
1	/	2	=	0	R	1



Read from bottom
to top: 100101_B

The Hexadecimal Number System



Name

- “hexa-” (Ancient Greek ἕξα-) \Rightarrow six
- “decem” (Latin) \Rightarrow ten

Characteristics

- Sixteen symbols
 - 0 1 2 3 4 5 6 7 8 9 A B C D E F
- Positional
 - $A13D_H \neq 3DA1_H$

Computer programmers often use hexadecimal or “hex”

- In C: 0x prefix (0xA13D, etc.)

Why?

Decimal-Hexadecimal Equivalence



<u>Decimal</u>	<u>Hex</u>
0	0
1	1
2	2
3	3
4	4
5	5
6	6
7	7
8	8
9	9
10	A
11	B
12	C
13	D
14	E
15	F

<u>Decimal</u>	<u>Hex</u>
16	10
17	11
18	12
19	13
20	14
21	15
22	16
23	17
24	18
25	19
26	1A
27	1B
28	1C
29	1D
30	1E
31	1F

<u>Decimal</u>	<u>Hex</u>
32	20
33	21
34	22
35	23
36	24
37	25
38	26
39	27
40	28
41	29
42	2A
43	2B
44	2C
45	2D
46	2E
47	2F
...	...

Integer-Hexadecimal Conversion



Hexadecimal to integer: expand using positional notation

$$\begin{aligned} 25_{\text{H}} &= (2 \cdot 16^1) + (5 \cdot 16^0) \\ &= 32 + 5 \\ &= 37 \end{aligned}$$

Integer to hexadecimal: use the shortcut

$$\begin{aligned} 37 / 16 &= 2 \text{ R } 5 \\ 2 / 16 &= 0 \text{ R } 2 \end{aligned}$$



Read from bottom
to top: 25_{H}

Binary-Hexadecimal Conversion



Observation: $16^1 = 2^4$

- Every 1 hexadecimal digit corresponds to 4 binary digits

Binary to hexadecimal

1	0	1	0	0	0	0	1	0	0	1	1	1	1	0	1	_B
A		1		3												_H

Digit count in binary number
not a multiple of 4 \Rightarrow
pad with zeros on left

Hexadecimal to binary

A		1		3												_H
1	0	1	0	0	0	0	1	0	0	1	1	1	1	0	1	_B

Discard leading zeros from
binary number if appropriate

Is it clear why programmers
often use hexadecimal?

iClicker Question

Q: Convert binary 101010 into decimal and hex

- A. 21 decimal, 1A hex
- B. 42 decimal, 2A hex
- C. 48 decimal, 32 hex
- D. 55 decimal, 4G hex

Hint: convert to hex first

The Octal Number System



Name

- “octo” (Latin) \Rightarrow eight

Characteristics

- Eight symbols
 - 0 1 2 3 4 5 6 7
- Positional
 - $1743_8 \neq 7314_8$



Computer programmers often use octal (so does Mickey!)

- In C: 0 prefix (01743, etc.)



Agenda



Number Systems

Finite representation of unsigned integers

Finite representation of signed integers

Finite representation of rational (floating-point) numbers

Integral Types in Java vs. C



	Java	C
Unsigned types	<code>char // 16 bits</code>	<code>unsigned char /* Note 2 */</code> <code>unsigned short</code> <code>unsigned (int)</code> <code>unsigned long</code>
Signed types	<code>byte // 8 bits</code> <code>short // 16 bits</code> <code>int // 32 bits</code> <code>long // 64 bits</code>	<code>signed char /* Note 2 */</code> <code>(signed) short</code> <code>(signed) int</code> <code>(signed) long</code>

1. Not guaranteed by C, but on `arm1ab`, `char` = 8 bits, `short` = 16 bits, `int` = 32 bits, `long` = 64 bits
2. Not guaranteed by C, but on `arm1ab`, `char` is unsigned

To understand C, must consider representation of both unsigned and signed integers

Representing Unsigned Integers



Mathematics

- Range is 0 to ∞

Computer programming

- Range limited by computer's **word** size
- Word size is n bits \Rightarrow range is 0 to $2^n - 1$
- Exceed range \Rightarrow **overflow**

Typical computers today

- $n = 32$ or 64 , so range is 0 to $2^{32} - 1$ or $2^{64} - 1$ (huge!)

Pretend computer

- $n = 4$, so range is 0 to $2^4 - 1$ (15)

Hereafter, assume word size = 4

- All points generalize to word size = 64, word size = n

Representing Unsigned Integers



On pretend computer

<u>Unsigned Integer</u>	<u>Rep</u>
0	0000
1	0001
2	0010
3	0011
4	0100
5	0101
6	0110
7	0111
8	1000
9	1001
10	1010
11	1011
12	1100
13	1101
14	1110
15	1111

Adding Unsigned Integers



Addition

			1
	3		0011 _B
+	10	+	1010 _B
--		--	----
	13		1101 _B

Start at right column
Proceed leftward
Carry 1 when necessary

			111
	7		0111 _B
+	10	+	1010 _B
--		--	----
	1		0001 _B

Beware of overflow

Results are mod 2^4

How would you detect overflow programmatically?

Subtracting Unsigned Integers



Subtraction

		111
10		1010 _B
- 7	-	0111 _B
--		----
3		0011 _B

Start at right column
Proceed leftward
Borrow when necessary

		1
3		0011 _B
- 10	-	1010 _B
--		----
9		1001 _B

Beware of overflow

Results are mod 2^4

How would you detect overflow programmatically?



Shifting Unsigned Integers

Bitwise right shift (\gg in C): fill on left with zeros

10 \gg 1 \Rightarrow 5
 1010_B 0101_B

10 \gg 2 \Rightarrow 2
 1010_B 0010_B

What is the effect arithmetically?
(No fair looking ahead)

Bitwise left shift (\ll in C): fill on right with zeros

5 \ll 1 \Rightarrow 10
 0101_B 1010_B

3 \ll 2 \Rightarrow 12
 0011_B 1100_B

What is the effect arithmetically?
(No fair looking ahead)

Results are mod 2^4

Other Operations on Unsigned Ints



Bitwise NOT (~ in C)

- Flip each bit

$\sim 10 \Rightarrow 5$

1010_{B} 0101_{B}

Bitwise AND (& in C)

- Logical AND corresponding bits

10	1010 _B
& 7	& 0111 _B
--	----
2	0010 _B

Useful for setting
selected bits to 0

Other Operations on Unsigned Ints



Bitwise OR: (| in C)

- Logical OR corresponding bits

10	1010 _B
1	0001 _B
--	----
11	1011 _B

Useful for setting
selected bits to 1

Bitwise exclusive OR (^ in C)

- Logical exclusive OR corresponding bits

10	1010 _B
^ 10	^ 1010 _B
--	----
0	0000 _B

$x \wedge x$ sets
all bits to 0

iClicker Question

Q: How do you set bit “n” (counting lsb=0) of unsigned variable “u” to zero?

A. $u \&= (0 \ll n);$

B. $u |= (1 \ll n);$

C. $u \&= \sim(1 \ll n);$

D. $u |= \sim(1 \ll n);$

E. $u = \sim u \wedge (1 \ll n);$

Aside: Using Bitwise Ops for Arith



Can use \ll , \gg , and $\&$ to do some arithmetic efficiently

$$x * 2^y == x \ll y$$

$$\bullet 3 * 4 = 3 * 2^2 = 3 \ll 2 \Rightarrow 12$$

$$x / 2^y == x \gg y$$

$$\bullet 13 / 4 = 13 / 2^2 = 13 \gg 2 \Rightarrow 3$$

$$x \% 2^y == x \& (2^y - 1)$$

$$\bullet 13 \% 4 = 13 \% 2^2 = 13 \& (2^2 - 1) \\ = 13 \& 3 \Rightarrow 1$$

Fast way to **multiply**
by a power of 2

Fast way to **divide**
unsigned by power of 2

Fast way to **mod**
by a power of 2

13	1101 _B
& 3	& 0011 _B
--	----
1	0001 _B

Many compilers will
do these transformations
automatically!

Aside: Example C Program



```
#include <stdio.h>
#include <stdlib.h>
int main(void)
{   unsigned int n;
    unsigned int count = 0;
    printf("Enter an unsigned integer: ");
    if (scanf("%u", &n) != 1)
    {   fprintf(stderr, "Error: Expect unsigned int.\n");
        exit(EXIT_FAILURE);
    }
    while (n > 0)
    {   count += (n & 1);
        n = n >> 1;
    }
    printf("%u\n", count);
    return 0;
}
```

What does it write?

How could you express this more succinctly?

Agenda



Number Systems

Finite representation of unsigned integers

Finite representation of signed integers

Finite representation of rational (floating-point) numbers

Sign-Magnitude



<u>Integer</u>	<u>Rep</u>
-7	1111
-6	1110
-5	1101
-4	1100
-3	1011
-2	1010
-1	1001
-0	1000
0	0000
1	0001
2	0010
3	0011
4	0100
5	0101
6	0110
7	0111

Definition

High-order bit indicates sign

0 \Rightarrow positive

1 \Rightarrow negative

Remaining bits indicate magnitude

$$0101_B = 101_B = 5$$

$$1101_B = -101_B = -5$$

Sign-Magnitude (cont.)



<u>Integer</u>	<u>Rep</u>
-7	1111
-6	1110
-5	1101
-4	1100
-3	1011
-2	1010
-1	1001
-0	1000
0	0000
1	0001
2	0010
3	0011
4	0100
5	0101
6	0110
7	0111

Computing negative

$\text{neg}(x) = \text{flip high order bit of } x$

$$\text{neg}(0101_{\text{B}}) = 1101_{\text{B}}$$

$$\text{neg}(1101_{\text{B}}) = 0101_{\text{B}}$$

Pros and cons

- + easy for people to understand
- + symmetric
- two representations of zero
- need different algorithms to add signed and unsigned numbers

Ones' Complement



<u>Integer</u>	<u>Rep</u>
-7	1000
-6	1001
-5	1010
-4	1011
-3	1100
-2	1101
-1	1110
-0	1111
0	0000
1	0001
2	0010
3	0011
4	0100
5	0101
6	0110
7	0111

Definition

High-order bit has weight -7

$$\begin{aligned} 1010_B &= (1 * -7) + (0 * 4) + (1 * 2) + (0 * 1) \\ &= -5 \end{aligned}$$

$$\begin{aligned} 0010_B &= (0 * -7) + (0 * 4) + (1 * 2) + (0 * 1) \\ &= 2 \end{aligned}$$

Ones' Complement (cont.)



<u>Integer</u>	<u>Rep</u>
-7	1000
-6	1001
-5	1010
-4	1011
-3	1100
-2	1101
-1	1110
-0	1111
0	0000
1	0001
2	0010
3	0011
4	0100
5	0101
6	0110
7	0111

Computing negative

$$\text{neg}(x) = \sim x$$

$$\text{neg}(0101_B) = 1010_B$$

$$\text{neg}(1010_B) = 0101_B$$

Similar pros and cons to sign-magnitude

Two's Complement



<u>Integer</u>	<u>Rep</u>
-8	1000
-7	1001
-6	1010
-5	1011
-4	1100
-3	1101
-2	1110
-1	1111
0	0000
1	0001
2	0010
3	0011
4	0100
5	0101
6	0110
7	0111

Definition

High-order bit has weight -8

$$\begin{aligned}1010_B &= (1 * -8) + (0 * 4) + (1 * 2) + (0 * 1) \\ &= -6\end{aligned}$$

$$\begin{aligned}0010_B &= (0 * -8) + (0 * 4) + (1 * 2) + (0 * 1) \\ &= 2\end{aligned}$$

Two's Complement (cont.)



<u>Integer</u>	<u>Rep</u>
-8	1000
-7	1001
-6	1010
-5	1011
-4	1100
-3	1101
-2	1110
-1	1111
0	0000
1	0001
2	0010
3	0011
4	0100
5	0101
6	0110
7	0111

Computing negative

$$\text{neg}(x) = \sim x + 1$$

$$\text{neg}(x) = \text{onescomp}(x) + 1$$

$$\text{neg}(0101_B) = 1010_B + 1 = 1011_B$$

$$\text{neg}(1011_B) = 0100_B + 1 = 0101_B$$

Pros and cons

- not symmetric (“extra” negative number)
- + one representation of zero
- + same algorithm adds unsigned numbers or signed numbers

Two's Complement (cont.)



Almost all computers today use two's complement to represent signed integers

- Arithmetic is easy!

Is it after 1980?
OK, then we're surely
two's complement



Hereafter, assume two's complement

Adding Signed Integers



pos + pos

			11
3		0011 _B	
+ 3	+	0011 _B	
--		----	
6		0110 _B	

pos + pos (overflow)

			111
7		0111 _B	
+ 1	+	0001 _B	
--		----	
-8		1000 _B	

pos + neg

			1111
3		0011 _B	
+ -1	+	1111 _B	
--		----	
2		0010 _B	

How would you detect overflow programmatically?

neg + neg

			11
-3		1101 _B	
+ -2	+	1110 _B	
--		----	
-5		1011 _B	

neg + neg (overflow)

			1 1
-6		1010 _B	
+ -5	+	1011 _B	
--		----	
5		0101 _B	

Subtracting Signed Integers



Perform subtraction
with borrows

or

Compute two's comp
and add

	11
3	0011 _B
- 4	- 0100 _B
--	----
-1	1111 _B



3	0011 _B
+ -4	+ 1100 _B
--	----
-1	1111 _B

-5	1011 _B
- 2	- 0010 _B
--	----
-7	1001 _B



	111
-5	1011
+ -2	+ 1110
--	----
-7	1001

Negating Signed Ints: Math



Question: Why does two's comp arithmetic work?

Answer: $[-b] \bmod 2^4 = [\text{twoscomp}(b)] \bmod 2^4$

$$\begin{aligned} & [-b] \bmod 2^4 \\ &= [2^4 - b] \bmod 2^4 \\ &= [2^4 - 1 - b + 1] \bmod 2^4 \\ &= [(2^4 - 1 - b) + 1] \bmod 2^4 \\ &= [\text{onescomp}(b) + 1] \bmod 2^4 \\ &= [\text{twoscomp}(b)] \bmod 2^4 \end{aligned}$$

See Bryant & O'Hallaron book for much more info

Subtracting Signed Ints: Math



And so:

$$[a - b] \bmod 2^4 = [a + \text{twoscomp}(b)] \bmod 2^4$$

$$\begin{aligned} & [a - b] \bmod 2^4 \\ &= [a + 2^4 - b] \bmod 2^4 \\ &= [a + 2^4 - 1 - b + 1] \bmod 2^4 \\ &= [a + (2^4 - 1 - b) + 1] \bmod 2^4 \\ &= [a + \text{onescomp}(b) + 1] \bmod 2^4 \\ &= [a + \text{twoscomp}(b)] \bmod 2^4 \end{aligned}$$

See Bryant & O'Hallaron book for much more info

Shifting Signed Integers



Bitwise left shift (<< in C): fill on right with zeros

3 << 1 ⇒ 6
0011_B 0110_B

-3 << 1 ⇒ -6
1101_B 1010_B

What is the effect arithmetically?

Results are mod 2^4

Bitwise right shift: fill on left **with ???**

Shifting Signed Integers (cont.)



Bitwise **arithmetic** right shift: fill on left **with sign bit**

6 >> 1 ⇒ 3
0110_B 0011_B

-6 >> 1 ⇒ -3
1010_B 1101_B

What is the effect arithmetically?

Bitwise **logical** right shift: fill on left **with zeros**

6 >> 1 ⇒ 3
0110_B 0011_B

-6 >> 1 ⇒ 5
1010_B 0101_B

What is the effect arithmetically???

In C, right shift (>>) could be logical or arithmetic

- Not specified by standard (happens to be arithmetic on armlab)
- **Best to avoid shifting signed integers**

Other Operations on Signed Ints



Bitwise NOT (~ in C)

- Same as with unsigned ints

Bitwise AND (& in C)

- Same as with unsigned ints

Bitwise OR: (| in C)

- Same as with unsigned ints

Bitwise exclusive OR (^ in C)

- Same as with unsigned ints

Best to avoid with signed integers

Agenda



Number Systems

Finite representation of unsigned integers

Finite representation of signed integers

Finite representation of rational (floating-point) numbers

Rational Numbers



Mathematics

- A **rational** number is one that can be expressed as the **ratio** of two integers
- Unbounded range and precision

Computer science

- Finite range and precision
- Approximate using **floating point** number

Floating Point Numbers



Like scientific notation: e.g., c is

$$2.99792458 \times 10^8 \text{ m/s}$$

This has the form

$$(\text{multiplier}) \times (\text{base})^{(\text{power})}$$

In the computer,

- **Multiplier** is called mantissa
- **Base** is almost always 2
- **Power** is called exponent

IEEE Floating Point Representation



Common finite representation: **IEEE floating point**

- More precisely: ISO/IEEE 754 standard

Using 32 bits (type `float` in C):

- 1 bit: sign (0⇒positive, 1⇒negative)
- 8 bits: exponent + 127
- 23 bits: binary fraction of the form $1.bbbbbbbbbbbbbbbbbbbbbbb$

Using 64 bits (type `double` in C):

- 1 bit: sign (0⇒positive, 1⇒negative)
- 11 bits: exponent + 1023
- 52 bits: binary fraction of the form $1.bbb$



Floating Point Example

Sign (1 bit):

- 1 \Rightarrow negative

11000001110110110000000000000000

32-bit representation

Exponent (8 bits):

- 10000011_B = 131
- 131 - 127 = 4

Mantissa (23 bits):

- 1.10110110000000000000000_B
- 1 + $(1*2^{-1}) + (0*2^{-2}) + (1*2^{-3}) + (1*2^{-4}) + (0*2^{-5}) + (1*2^{-6}) + (1*2^{-7}) = 1.7109375$

Number:

- -1.7109375 * 2⁴ = -27.375

When was floating-point invented?



Answer: long before computers!

mantissa

noun

decimal part of a logarithm, 1865, from Latin *mantisa* “a worthless addition, makeweight,” perhaps a Gaulish word introduced into Latin via Etruscan (cf. Old Irish *meit*, Welsh *maint* “size”).

COMMON LOGARITHMS $\log_{10}x$

x	0	1	2	3	4	5	6	7	8	9.	Δ_m	1	2	3
												+		
50	.6990	6998	7007	7016	7024	7033	7042	7050	7059	7067	9	1	2	3
51	.7076	7084	7093	7101	7110	7118	7126	7135	7143	7152	8	1	2	2
52	.7160	7168	7177	7185	7193	7202	7210	7218	7226	7235	8	1	2	2
53	.7243	7251	<u>7259</u>	7267	7275	7284	7292	7300	7308	7316	8	1	2	2
54	.7324	7332	7340	7348	7356	7364	7372	7380	7388	7396	8	1	2	2
55	.7404	7412	7419	7427	7435	7443	7451	7459	7466	7474	8	1	2	2

Floating Point Consequences



“Machine epsilon”: smallest positive number you can add to 1.0 and get something other than 1.0

For float: $\varepsilon \approx 10^{-7}$

- No such number as 1.000000001
- Rule of thumb: “almost 7 digits of precision”

For double: $\varepsilon \approx 2 \times 10^{-16}$

- Rule of thumb: “not quite 16 digits of precision”

These are all *relative* numbers

Floating Point Consequences, cont



Just as decimal number system can represent only some rational numbers with finite digit count...

- Example: $1/3$ *cannot* be represented

<u>Decimal</u> <u>Approx</u>	<u>Rational</u> <u>Value</u>
.3	3/10
.33	33/100
.333	333/1000
...	

Binary number system can represent only some rational numbers with finite digit count

- Example: $1/5$ *cannot* be represented

<u>Binary</u> <u>Approx</u>	<u>Rational</u> <u>Value</u>
0.0	0/2
0.01	1/4
0.010	2/8
0.0011	3/16
0.00110	6/32
0.001101	13/64
0.0011010	26/128
0.00110011	51/256
...	

Beware of **roundoff error**

- Error resulting from inexact representation
- Can accumulate
- Be careful when comparing two floating-point numbers for equality

iClicker Question

Q: What does the following code print?

```
double sum = 0.0;
int i;
for (i = 0; i < 10; i++)
    sum += 0.1;
if (sum == 1.0)
    printf("All good!\n");
else
    printf("Yikes!\n");
```

- A. All good!
- B. Yikes!
- C. Code crashes
- D. Code enters an infinite loop

Summary



The binary, hexadecimal, and octal number systems

Finite representation of unsigned integers

Finite representation of signed integers

Finite representation of rational (floating-point) numbers

Essential for proper understanding of

- C primitive data types
- Assembly language
- Machine language