

#### Precept 2: Non-preemptive Scheduler

#### COS 318: Fall 2019



- Precept: Monday 09/30 & Tuesday 10/01, 7:30pm - 8:20pm
- Design Review: Monday 10/07 & Tuesday 10/08, 3 7pm
- **Due:** Sunday 10/13, 11:55pm



- Goal: Build a non-preemptive kernel that can switch between different tasks (task = process or kernel thread)
- Read the project spec for more details
- Start early



- Current running task loses CPU or running state
- in the following scenarios:
- 1. Yield
- 2. Block: I/O operation, Lock (thread)
- 3. Exit

### What is a Non-Preemptive Kernel?



COS 318: Life: go to class(); have fun(); go\_to\_precept(); yield(); yield(); play(); thinking (); yield(); design review() do random stuff() yield(); yield(); coding(); ... exit();

### What is a Non-Preemptive Kernel?







- 1. Process Control Blocks (PCBs)
- 2. User and Kernel Stack
- 3. Basic System Call Mechanism
- 4. Context Switching
- 5. Mutual Exclusion



- **Protected Mode:** No need to worry about segment registers again!
- Non-Preemptive Tasks: Run until they yield, block, or exit
- Fixed Number of Tasks: Allocate per-task state (PCB) statically in your program
- Fixed Task Stack Size

# 1. Process Control Block (PCB)



- Defined in kernel.h and initialized in kernel.c:\_start
- What is its purpose?
- What should be in the PCB?
  - Process ID (PID)
  - Stack Info
  - Registers
  - CPU Time
  - Etc.

## 2. Allocating Stacks



- Allocate separate user-space stacks for each task in kernel.c:\_start()
- In theory, processes have two stacks:
  - 1. User Stack: For the process to use
  - 2. Kernel Stack: For the kernel to use when executing system calls on behalf of theprocess
  - Option: In this assignment, you can opt to use only one stack
- Kernel threads need only one stack
- 4kB per stack is enough





- So user processes can ask for kernel services
- Standard Procedure:
  - Push system call ID + arguments onto stack
  - Interrupt /trap: elevate privileges + jumps intokernel
- NOT the case for this assignment...





- User processes provided with syslib.h
- These functions:
  - Load kernel entry point address from known location in memory (ENTRY\_POINT)
  - Push system call ID onto stack + call kernel\_entry function

# 3. System Calls - kernel\_entry

- kernel\_entry address stored at ENTRY\_POINT (0xf00)
- Saves registers + switches to kernel stack
- Does the reverse when exiting the kernel

0x00000	BIOS
0x00F00	ENTRY_POINT
0x01000	Kernel
0x10000	Process 1
0x20000	Process 2
0x30000	Process 3
0x40000	Stacks
	Kernel Stack
0x9FFFE	(set by bootblock.s)
0xA0000	Video RAM





- Goal: safely switch currently running task
- When does this happen?
  - Preemptive OS: typically when the OS tells you to
  - Non-preemptive OS: when task yields or exits

## 4. Context Switch - Responsibilities



- 1. Save task state into PCB
- 2. Push current PCB into ready or block queue
- 3. Choose new task from ready queue + pop its PCB
- 4. Restore new task state + run it

# 4. Context Switch - Saving State



- Tasks should not care what happens while its not running save current state in its PCB:
  - General purpose registers (including%esp)
  - Flags
- What about the instruction pointer?

# 4. Context Switch - Scheduling



- Kernel must maintain:
  - Ready Queue: tasks ready to be run
  - Blocked Queue: tasks blocked on some resource
- Which task runs next?
  - Regular: round-robin

EC: lowest run-time



- Spinlock implementation is provided, you must implement a blockinglock
  - See spec for precise requirements
- No preemption => no race conditions \*
- Exactly one correct trace



- util.c:get\_timer returns # cycles since boot
- Implement parts of th3 and process3
  - process3 included twice in task list be able to distinguish between the two executions

## Tips + Things to think about...



- What should you do when a kernel thread is run for the first time?
- What state should be saved to PCB? In what order?
- Get queue working in user space
- Code and test incrementally



(Monday, 10/08) Answer the questions:

- **Process Control Block:** What will be in your PCB and what will it be initialized to?
- **Context Switching:** How will you save and restore a task's context? Should anything special be done for the first task?
- **Processes:** What, if any, are the differences between threads and processes and how they are handled?
- **Mutual Exclusion:** What's your plan for implementing mutual exclusion?
- Scheduling: Look at the project web page for an execution example.



# Questions?